


# **USB Firmware Update Manual**


## Preparatory Work

- Windows PC run windows XP/7/8/10/11
- TPSXXX-TB016-TB026 Utility.exe from TMD
- USB cable for controller
- **TMD PCAP controller "TPS7721-V1" with "SWITCH KEY"**




## Firmware Update


1. Connect controller to windows PC, Run “TPSXXXX-TB016-TB026 Utility.exe” on PC, Click “Update” for run “Firmware Update.exe”





2. Press “Browse” Button, add “.Rom ” file into application .




### 3. Select correct port for update firmware



4. Press “SWITCH KEY” of controller and keep hold 10seconds, then release, the controller will into DFU mode, the “Download” button of utility will be activated, then press the “Download”button.



5. Wait download process finish, until dialog windows show you “Download completed”.



6. Any exception please repeat step 2 to step 5.